

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

THINC-API
Installation Manual

Document No.: S5015-007-11

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

Revision History

Date	Version	Description	Author
05/10/2007	S5015-007-00	Installation Manual	LHuynh
10/05/2007	S5015-007-01	Add Installation For Custom Application section	LHuynh
2/22/2008	S5015-007-02	Add 4.3, 4.4 section and revise section 7.2. Change name of release note for Lathe and MC and installation manual to actual name (LatheReleaseNote/MCReleaseNote, InstallationManual)	LHuynh
4/11/2008	S5015-007-03	<ul style="list-style-type: none"> - Revise section 3.0 Requirement - Revise section 3.1 Compatibles - Revise section 4.1.1 Run Setup - Revise section 4.1.2 Setup Type - Revise section 4.3 Install License File - Revise section 4.4.1.2 Validation - Remove section 4.4.1.3.2 OSP System software - Revise 5.1.1.1 Setup - Revise section 7.2 License -Revise section 7.3 Best Practice 	LHuynh
6/02/2008	S5015-007-04	<ul style="list-style-type: none"> - Revise section 4.3 Install license file - Revise section 5.1.1 Repair 	LHuynh
10/27/2008	S5015-007-05	Revise 4.1.5 Finish Revise 4.2.5 Finish Revise 5.1.1.3 Finish	LHuynh
02/14/2014	S5015-007-06	Revised all THINC API to THINC-API	LHuynh
11/17/2015	S5015-007-07	Revised for public release 1.18.0.0	LHuynh
11/17/2016	S5015-007-08	Revised for public release 1.19.0.0 Sessions: 1.4, 4.0, 4.5, 6.0, 7	LHuynh
08/07/2017	S5015-007-09	Revised for public release 1.20.0.0 Sessions: 3.1, 4.2, 4.5.2.4, 6.1	LHuynh
03/07/2018	S5015-007-10	Revised for public release 1.21.1.0 Sessions: 3.1 Compatibles 4.2 Desktop Installation	LHuynh

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

		4.5.1.2 Validation 4.5.2.4 Logging Service for .NET Framework 4.0 THINC-API libraries 6.1 Machine Installation	
06/03/2024	S5015-007-11	Support OAC License File	LHuynh

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

Table of Contents

1.	Introduction	6
1.1	Purpose	6
1.2	Scope	6
1.3	Definitions, Acronyms, and Abbreviations	6
1.4	Overview	6
2.	References	6
3.	Requirements	6
3.1	Compatibles	6
4.	Installation Instruction	7
4.1	Machine/NC Master Installation	7
4.1.1	Run Setup	7
4.1.2	Setup Type	9
4.1.3	Setup	9
4.1.4	Installing	10
4.1.5	Finish	11
4.2	Desktop Installation	12
4.2.1	Run setup	12
4.2.2	Setup Type	13
4.2.3	Setup	14
4.2.4	Installing	14
4.2.5	Finish	15
4.3	Upgrade Installation	15
4.3.1	Run setup	16
4.3.2	Installing	17
4.3.3	Finish	18
4.4	Install License file	19
4.5	Validate Installation	19
4.5.1	THINC-API Libraries	19
4.5.1.1	Run THINC sample application	19
4.5.1.2	Validation	19
4.5.1.3	Errors	23
4.5.2	Logging Service & Logging Service Client Application	33
4.5.2.1	Logging Service	33
4.5.2.2	Logging Library	36
4.5.2.3	Logging Service Client Application	36
4.5.2.4	Logging Service for .NET Framework 4.0 THINC-API libraries	37
5.	Repair/Uninstall THINC-API	38
5.1	Repair/Un-install	38
5.1.1	Repair	39
5.1.1.1	Run Setup	39
5.1.1.2	Setup	42
5.1.1.3	Finish	43
5.1.2	Uninstall	43
5.1.2.1	Run setup	43

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

5.1.2.2	Setup Status	46
5.1.2.3	Finish	47
6.	Installation Files	48
6.1	Machine Installation	49
6.1.1	Lathe	49
6.1.1.1	GAC Folder	49
6.1.1.2	Okuma Folders	49
6.1.2	Machining Center	50
6.1.2.1	GAC Folder	50
6.1.2.2	Okuma Folders	50
6.1.3	Grinder	51
6.1.3.1	GAC Folder	51
6.1.3.2	Okuma Folders	51
6.2	Desktop Installation	52
7.	Installation for Custom Application	52
7.1	THINC-API Spec. Code	52
7.2	License	53
7.2.1	Flexnet License File	53
7.2.2	OAC License File	55
7.3	Installation	60
7.4	Public Release	61
7.5	Best Practice	61

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

Installation Manual

1. Introduction

1.1 Purpose

The purpose of this document is providing the instruction of how to install THINC-API on machine, NC Master, and desktop PC. It also provides information on how to repair and uninstall THINC-API.

1.2 Scope

This installation will cover installing THINC-API for different machine types, and desktop PC.

1.3 Definitions, Acronyms, and Abbreviations

GAC – Global Assembly Cache Windows folder located in ‘C:\WINDOWS\assembly’

1.4 Overview

The THINC-API setup application will automatically detect if this installation is for Machine/NC master or desktop PC.

- The Machine/NC Master installation will install:
 - THINC-API document, and sample application using THINC-API
 - THINC-API libraries to enable building and running THINC-API application to run.
- Desktop installation will installs all THINC-API libraries, sample application, help file
 - THINC-API document, and sample application using THINC-API
 - THINC-API libraries to enable building THINC-API application.

The THINC-API setup application also detects and installs the correct THINC-API library files for lathe, machining center, and grinder when installing for Machine/NC Master.

For desktop installation, all libraries can be installed altogether if needed

2. References

None

3. Requirements

The THINC-API setup application requires running under Administrator user account only. It also requires to run under Windows mode only (NC is not running). If NC is running, it requires rebooting the machine to Windows mode.

3.1 Compatibles

THINC-API must be installed on the OSP-P100II/P200 or newer OSP-P controls in order to access to machine data. It requires .NET framework 4.0 for Lathe, Machining Center and Grinder.

THINC-API has been tested on the following platforms:

- Microsoft Windows XP Professional Embedded with SP3

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

- Microsoft Windows 7 x86 with SP1


THINC-API libraries can be used with Microsoft Visual Studio 2010 or newer Visual Studio version to develop custom Windows application.

4. Installation Instruction

4.1 Machine/NC Master Installation



4.1.1 Run Setup

Run the THINC-API-Setup.exe program from the provided installation disk on Machine/NC Master



During this stage, the installation will evaluate OSP system file to ensure that it can support current installation. If not, the setup will generate an error message and terminate the installation.


THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



Press Next to advance to the next page

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024


4.1.2 Setup Type



Select the appropriate option and click Next to continue with the installation process.

4.1.3 Setup

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024




In this setup dialog, information on the selected options will be displayed.

Click Next to continue with the installation process or click Back to review/ change any settings.


4.1.4 *Installing*

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



At any time, you can press Cancel button to terminate the installation.

4.1.5 Finish



THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

Click Finish to just finish the installation process.

4.2 Desktop Installation

All 3 libraries for Lathe, Machining Center, and Grinder can be installed when desktop installation is detected. The installation will consider desktop installation when there is no OSP-P folder on C drive.


All libraries and applications will be installed for each selection of machine types.

Note: An upgrade installation might not be able to install all 3 libraries if the previous version of THINC-API installed on desktop is 1.18.0.0 or older.


D drive is also required for Desktop Installation

4.2.1 Run setup

Run the THINC-API-Setup.exe program from the provided installation disk on desktop PC.




THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



Press Next to advance to the next page


4.2.2 Setup Type



THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

Select the appropriate option and click Next to continue with the installation process.

4.2.3 Setup




In this setup dialog, information on the selected options will be displayed.

Click Next to continue with the installation process or click Back to review/ change any settings.


4.2.4 Installing

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



At any time, you can press Cancel button to terminate the installation.

4.2.5 Finish



Click Finish to just finish the installation process.

4.3 Upgrade Installation


If the target machine or PC already has the previous version THINC-API then the installation will enter the

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024


upgrade installation mode.

4.3.1 Run setup

Run the THINC-API-Setup.exe program from the provided installation disk on Machine/NC Master





Click “Yes” button to perform upgrade THINC-API to the newer version



During this stage, the installation will evaluate OSP system file to ensure that it can support current installation. If not, the setup will generate an error message and terminate the installation.


THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



Press Next to advance to the next page


4.3.2 Installing

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



At any time, you can press Cancel button to terminate the installation.

4.3.3 Finish



Click Finish to just complete the installation process.

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

4.4 Install License file

When THINC-API Setup program runs it will install either demo or permanent license version.

It is best to obtain the license file that supports the latest release of THINC-API libraries version although your application only requires an older THINC-API version.

License file can also manually copy to the D:\Program files\Okuma\License folder.

By default, the current version of installation will always copy the license file included with the Setup to the destination folder.

Note: Each Public Release of THINC-API always has a license file that supports the latest version of all THINC libraries. All applications developed with THINC-API use the same license file as long as THINC-API library version that your application compiled with is less than or equal to library version in the license file.

4.5 Validate Installation

4.5.1 THINC-API Libraries

For machine/NC Master installation, the test sample application can be run to ensure that THINC-API libraries can be supported under current machine configuration. By design, THINC-API libraries are tightly integrated with NC OSP System software. Therefore, a certain file version of NC OSP System files must be met in order to support all functions in the libraries.

Note: Per function call in the libraries also depends on machine options, spec. code, NC Control software version etc...

4.5.1.1 Run THINC sample application

Based on OSP Software System files, the Setup program will only install the appropriate libraries. It will install either Lathe/Machining Center/Grinder libraries.

Using Windows Explore to navigate to D drive and subfolder:

Lathe: D:\Program Files\Okuma\THINC API\ThincLathe\bin

MC: D:\Program Files\Okuma\THINC API\ThincMC\bin

Grinder: D:\Program Files\Okuma\THINC API\ThincMC\bin

Run THINC sample application by double clicking on ThincLathe.exe, ThincMC.exe, and ThincGrinderApp.exe for Lathe/Machining Center/Grinder, respectively.

4.5.1.2 Validation

4.5.1.2.1 THINC-API Sample Applications

If current OSP System software can support current version of THINC-API libraries installed on machine, a Windows Form should be displayed without any error message as shown:

Note: Per function call in the libraries also depends on machine options, spec. code, NC Control software version etc...

Machining Center Test application

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

Sample THINC-API (Machining Centers)

P300 Tools

ATC

P300 ATC

ATC Sub Panel

Machine

Workpiece

Optional Parameter

Spec

Tools 2-1

Coolant

Macman Operating History

MacMan I

Group No.

1

Tool/Station

1

Compensation No

Data Unit :

SET

P300 S(MP) / M

Tool Offset

Get

Set

Ad

Cal

1

0

Tool Wear Offset

Get

Set

Ad

1

0

Tool Life - SET

Get

Set

1

0

Cutter Radius Wear Offset

Get

Set

Ad

Cal

1

0

Cutter Radius Offset

Get

Set

Ad

1

0

Tool Life - LEFT

Get

Set

1

0

Tool Life STATUS

Get

Set

1

Tool Group No.

Get

Set

1

0

Tool Max Speed

Get

Set

1

0

Tool Type

Get

1

Tool Name

Get

Set

1

0

Get Registered Tool List (P300S/L)

Update

Get Attached Tool List (P300S/L)

Get All Tool List (P300S/L)

Clear

Lathe Test application:

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

4.5.1.2.2 THINC-API Notifier

There is a Windows Service called 'Okuma API Notifier' which will be installed on machine, NC Master, and desktop PC. It indicates the status of THINC-API as an icon in the system taskbar.

There are 4 states of THINC-API Notifier as shown below:

1/ Waiting State (API white-background icon) – NC is not running yet. THINC-API is not initialized yet.



2/ Initializing state (API Yellow-background icon) – NC is started and THINC-API is initializing.



3/ Initialized (API Green-background icon) – THINC-API is successfully initialized with NC and is ready for exchanging data.




4/ Failed to initialize (API red-background icon) – NC is started and THINC-API cannot communicate with NC due to some reasons.



By clicking on the icon, it will bring up a dialog and shows status of THINC-API with message, for example:

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024




4.5.1.3 Errors

4.5.1.3.1 NC Not Running

4.5.1.3.1.1 DATA-API


THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024




Problem: THINC-API libraries fail to initialize due to NC running condition.

Solution: Start application developed with THINC-API libraries after NC is running.
Custom applications can utilize 'Startup Service' developed by OKUMA to ensure that your custom application starts after NC started.

4.5.1.3.1.2 Command API



THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



Problem: THINC-API libraries fail to initialize due to NC running condition.

Solution: Start application developed with THINC-API libraries after NC is running.
Custom applications can utilize 'Startup Service' developed by OKUMA to ensure that your custom application starts after NC started.

4.5.1.3.2 THINC-API dependency library files

THINC-API will check the following files in NC OSP system software for the same or greater file version.

For Lathe:

LDATAPI.dll
LCMDAPI.exe
Softswitch.exe

For MC:

MDATAPI.dll
MCMDAPI.exe
Softswitch.exe

For Grinder:


GDATAPI.dll
GCMDAPI.exe
Softswitch.exe

And PIODLIB.dll library

4.5.1.3.2.1 Incorrect file version

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

For any reason if the above files listed for Lathe/MC have incorrect file version, a dialog box will display and show the error message of what causing THINC-API sample application fails to run correctly.




The error message shows an incorrect file version:

- Operation: Failed to Validate dependency files version
- Problem: Okuma.CMDATAPI.dll requires C:\OSP-P\SharedDll\MDATAPI.dll version 1.0.2.1 or above.

Solution: Re-Install/Install THINC-API again if any of the above file listed for Lathe/MC has incorrect file version.

4.5.1.3.2.2 Missing Dependency files

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



The error message shows a missing file:


- Operation: Failed to Validate dependency files version
- Problem: Okuma.CMDATAPI.dll requires C:\OSP-P\SharedDll\MDATAPI.dll file.

Solution: If any of the above files listed for Lathe/MC are missing, then an installation of THINC-API to the latest version is needed.

4.5.1.3.3 THINC-API library files

4.5.1.3.3.1 Missing library file

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



All applications developed with .NET THINC-API libraries are required to include an exact version of THINC-API libraries with the custom installation. THINC-API libraries compiled with application should be installed with your application folder.

The above error message shows that THINC-API library named Okuma.CLDATAPI.dll cannot be found at the folder where the application runs from.

Solution: Include THINC-API libraries compiled in your application with your custom setup and re-install your application with new setup.

4.5.1.3.3.2 Incorrect library file version

Problem: THINC-API libraries fail to load due to incorrect library version.

Solution: All custom applications developed with THINC-API libraries must install THINC-API libraries in the application's installation folder and must have the same file version as the libraries version compiled with.


4.5.1.3.4 License file

At first run, THINC-API will validate its license file named Okuma.api.xml or Okuma.api.lic located in D:\Program Files\Okuma\Licenses folder for correct version per THINC-API library file.

Note: If Okuma.api.xml license is in the license folder, THINC-API will only validate its license with this license file ONLY. Only Okuma.api.xml license file can support alphanumeric machine serial number.

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

4.5.1.3.4.1 Missing license file




The error message shows a missing file:

- Operation: Failed to check out license feature name 'Okuma.CMDATAPI.All' feature version '1.3' at location 'D:\Program files\Okuma\Licenses\okuma.api.lic'
- Problem: Cannot find license file (-1, 359:2 "No such file or directory")

Solution: If the license is missing, then an installation of THINC-API to the latest version is needed.

4.5.1.3.4.2 Incorrect license file version

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024




The error message shows an incorrect license version for a particular THINC-API library:

- Operation: Failed to check out license feature name 'Okuma.CMDATAPI.All' feature version '1.3' at location 'D:\Program files\Okuma\Licenses\okuma.api.lic'
- Problem: License file does not support this version. (-21, 126)

Solution: Installation of THINC-API to the latest version is needed.

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

4.5.1.3.4.3 Invalid license file




The error message shows an invalid license file for a particular THINC-API library:

- Operation: E01080013001 Failed to check out license feature name 'Okuma.CMDATAPI.All', feature version '1.3' at location 'D:\Program files\Okuma\Licenses\okuma.api.lic'
- Problem: Invalid (inconsistent) license key. (-8,523). Probably, the license file has been modified.

Solution: Un-install current version and install THINC-API to the latest version.

4.5.1.3.4.4 Expired license file

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024




The error message shows an expired license file for a particular THINC-API library:

- Operation: E01080013001 Failed to check out license feature name 'Okuma.CLDATAPI.All', feature version '1.3' at location 'D:\Program files\Okuma\Licenses\okuma.api.lic'
- Problem: Feature has expired (-10,32)

Solution: Install THINC-API to the latest version with permanent license file. Please see section '4.3 Install External License file' for installing external license file.

4.5.1.3.4.5 Flexnet License library

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



The error message shows that a dependency library for THINC-API library cannot find in GAC (Global Assembly Cached (\Windows\assembly) folder:

- Problem: File or assembly name Okuma.FlexNet, or one of its dependencies, was not found.

Solution: Install THINC-API to the latest version.

4.5.1.3.4.6 OAC License library

For license file named Okuma.api.xml, the following must be installed with Windows System folder:
Okuma.LicensingMgr.dll and Okuma.LicenseLib.dll


4.5.2 Logging Service & Logging Service Client Application

4.5.2.1 Logging Service

At first run, THINC-API libraries will connect with Logging Service utility.

The Logging Service could fail to load correctly as indicated below:

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024




The error message shows a missing file:

- Operation: Failed to load Logging Service
- Problem: Failed to locate database file at D:\Program Files\Okuma\LoggingService\log.fdb

Solution: Re-install or install THINC-API libraries to the latest version.

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024




The error message shows that the Logging Service server is not running on the local machine (localhost):

- Operation: Failed to load Logging Service
- Problem: ApiLog.initConnection: Unable to complete network request to host "localhost"

Solution:

Make sure that FireBird server status is running. If not, start the FireBird server from Service

Windows




Or

Re-install or install THINC-API libraries to the latest version.

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

4.5.2.2 Logging Library



The error message shows that a dependency library for THINC-API library cannot find in GAC (Global Assembly Cached \Windows\assembly) folder:

- Problem: File or assembly name Okuma.ApiLog or one of its dependencies, was not found.


Solution: Install THINC-API to the latest version.

4.5.2.3 Logging Service Client Application

The Logging Client application is a utility that allows one to view all logging records logged by THINC-API libraries at different logging level.

A successful loading of LoggingServiceClient application is shown below:

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



LoggingServiceClient application could fail to load up correctly if the logging database file is missing or Logging Service does not start yet.

Please refer to section 4.4.2.1 and 4.4.2.2 for correcting the problems.

4.5.2.4 Logging Service for .NET Framework 4.0 THINC-API libraries

THINC-API libraries compiled with .NET Framework will not use Okuma.ApiLog.dll library any more. It will use Okuma.ApiLog2.dll instead.
The following libraries and application are used for logging service and installed in D:\Program files\Okuma\LoggingService2 folder:
Okuma.Api.LogService.WinHost.exe
Okuma.Api.LogService.dll
System.Data.SQLite.dll
ApiLog2

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

⚙️ O2FLASH		Started	Automatic (...)	Local Syst..
⚙️ Office Source Engine	Saves install...		Manual	Local Syst..
⚙️ Office Software Protection Platform	Enables the ...	Started	Manual	Network S.
⚙️ OfficeScan Common Client Solution Frame...	Manages a...	Started	Manual	Local Syst..
⚙️ OfficeScan NT Listener	Receives co...	Started	Automatic	Local Syst..
- ⚙️ OfficeScan NT Proxy Service	Scans netw...		Manual	Local Syst..
⚙️ OfficeScan NT RealTime Scan	Performs Re...	Started	Automatic	Local Syst..
⚙️ Offline Files	The Offline ...		Disabled	Local Syst..
⚙️ OKUMA API Logging Service Win Host	Logging Ser...		Automatic	Local Syst..
⚙️ Okuma API Notifier	Detects that...		Automatic	Local Syst..
⚙️ OkumaWinSvcHostedCalcService	OKUMA WC...		Disabled	Local Syst..

The logging service client application is part of Lathe, Machining Center, and Grinder Test application as shown below:

The screenshot shows the 'THINC-API For Grinder' application window with the 'API Logging Service' tab selected. The 'Log Information' section contains search filters: 'Starting Date' (11/14/2016 15:15:41), 'Ending Date' (11/14/2016 15:15:41), 'Application Name Like:', 'Class Name Like:', 'Function Name Like:', 'I/O Parameters Like:', 'Logging Level <=: logException', and 'Message Like:'. A 'Display Log Records' button is present. Below the filters is a table with the following columns: Date Logged, Application Name, Class Name, Method Name, I/O Parameters, Logging Level, and Message. The table is currently empty. At the bottom right, there is a 'Clear Message' button.

5. Repair/Uninstall THINC-API

5.1 Repair/Un-install

If THINC-API already installed, the setup will ask for either Repair or Remove the current THINC-API installation.

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024


5.1.1 Repair

The setup will try to re-install all files current being installed on machine.



5.1.1.1 Run Setup

Run the THINC-API from Add or Remove Programs or source of media

Note: The original source of THINC-API setup must be available and accessible from Windows drive.




THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



Select the “Repair” option and press Next to continue the process

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024


If you select 'Remove' and press Next, the installation will ask for your confirmation to remove current THINC-API installation.



Click Yes to continue with the installation process or click No to review/change any settings.

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024


5.1.1.2 Setup



At any time, you can press Cancel button to terminate the installation.

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

5.1.1.3 Finish





Click Finish to just finish the installation process.


5.1.2 Uninstall

5.1.2.1 Run setup

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024




THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



Select 'Remove' and press Next.

The installation will ask for your confirmation to remove current THINC-API installation.


THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



Click Yes to continue with the installation process or click No to review/change any settings.

5.1.2.2 Setup Status


THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



At any time, you can press Cancel button to terminate the installation.

5.1.2.3 Finish

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024



Click Finish to just finish the installation process.

6. Installation Files

The following files are considered *THINC-API libraries* which are included in the subfolder *program files\Okuma\THINC API\Bin*:

- Okuma.CLDATAPI.dll
- Okuma.CLCMDAPI.dll
- Okuma.CLDATAPI.xml (Visual Studio Brower Help files)
- Okuma.CLCMDAPI.xml (Visual Studio Brower Help files)

- Okuma.CMDATAPI.dll
- Okuma.CMCMDAPI.dll
- Okuma.CMDATAPI.xml (Visual Studio Brower Help files)
- Okuma.CMCMDAPI.xml (Visual Studio Brower Help files)

- Okuma.CGDATAPI.dll
- Okuma.CGCMDAPI.dll
- Okuma.CGDATAPI.xml (Visual Studio Brower Help files)
- Okuma.CGCMDAPI.xml (Visual Studio Brower Help files)

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

6.1 Machine Installation

6.1.1 *Lathe*

6.1.1.1 GAC Folder

THINC-API libraries:

- Okuma.CLDATAPI.dll
- Okuma.CLCMDAPI.dll

Logging Service library:

- Okuma.ApiLog2.dll
- Okuma.Api.LogService.dll
- Okuma.Api.LogService.Data.dll

Dependency library files for THINC-API:

- Okuma.Interop.LCMDAPI.dll

6.1.1.2 Okuma Folders

THINC-API Release notes:

D:\Program files\Okuma\THINC API \ LatheReleaseNote.pdf

THINC-API Installation Manual:

D:\Program files\Okuma\THINC API \InstallationManual.pdf

THINC-API license file:

D:\Program files\Okuma\Licenses\Okuma.api.lic

THINC-API license file:

D:\Program files\Okuma\Licenses\Okuma.api.xml

THINC-API Help file:

D:\Program files\Okuma\THINC API\Help\THINLathe.chm

THINC-API Sample application folder:

D:\Program files\Okuma\THINC API \THINCLathe

THINC-API libraries and Visual Studio Brower Help files:

D:\Program files\Okuma\THINC API \bin

- Okuma.CLDATAPI.dll
- Okuma.CLCMDAPI.dll
- Okuma.CLDATAPI.xml (Visual Studio Brower Help files)
- Okuma.CLCMDAPI.xml (Visual Studio Brower Help files)

Logging Service folder:

D:\Program Files\Okuma\LoggingService2

- ApiLog2
- Okuma.Api.LogService.dll
- Okuma.Api.LogService.WinHost.exe
- Okuma.Api.LogService.WinHost.exe.config
- System.DataSQLite.dll

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

6.1.2 Machining Center

6.1.2.1 GAC Folder

THINC-API libraries:

- Okuma.CMDATAPI.dll
- Okuma.CMCMDAPI.dll

Logging Service library:

- Okuma.ApiLog2.dll
- Okuma.Api.LogService.dll
- Okuma.Api.LogService.Data.dll

Dependency library files for THINC-API:

- Okuma.Interop.MCMDAPI.dll

6.1.2.2 Okuma Folders

THINC-API Release notes:

D:\Program files\Okuma\THINC API \MCReleaseNote.pdf

THINC-API Installation Manual:

D:\Program files\Okuma\THINC API \InstallationManual.pdf

THINC-API license file for both Lathe & MC:

D:\Program files\Okuma\Licenses\Okuma.api.lic

THINC-API license file for both Lathe & MC:

D:\Program files\Okuma\Licenses\Okuma.api.xml

THINC-API Help file:

D:\Program files\Okuma\THINC API\Help\THINCMC.chm

THINC-API Sample application folder:

D:\Program files\Okuma\THINC API \THINCMC

THINC-API libraries and Visual Studio Brower Help files:

- D:\Program files\Okuma\THINC API \bin
- Okuma.CMDATAPI.dll
 - Okuma.CMCMDAPI.dll
 - Okuma.CMDATAPI.xml (Visual Studio Brower Help files)
 - Okuma.CMCMDAPI.xml (Visual Studio Brower Help files)

Logging Service folder:

- D:\Program Files\Okuma\LoggingService2
- ApiLog2
 - Okuma.Api.LogService.dll
 - Okuma.Api.LogService.WinHost.exe
 - Okuma.Api.LogService.WinHost.exe.config
 - System.DataSQLite.dll

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

6.1.3 Grinder

6.1.3.1 GAC Folder

THINC-API libraries:

- Okuma.GGDATAPI.dll
- Okuma.CGCMDDAPI.dll

Logging Service library:

- Okuma.ApiLog2.dll
- Okuma.Api.LogService.dll
- Okuma.Api.LogService.Data.dll

Dependency library files for THINC-API:

- Okuma.Interop.GCMMDDAPI.dll

6.1.3.2 Okuma Folders

THINC-API Release notes:

D:\Program files\Okuma\THINC API \ReleaseNote.pdf

THINC-API Installation Manual:

D:\Program files\Okuma\THINC API \InstallationManual.pdf

THINC-API license file for Lathe, MC, and Grinder:

D:\Program files\Okuma\Licenses\Okuma.api.lic

THINC-API license file for Lathe, MC, and Grinder:

D:\Program files\Okuma\Licenses\Okuma.api.xml

THINC-API Help file:

D:\Program files\Okuma\THINC API\Help\THINCGrinder.chm

THINC-API Sample application folder:

D:\Program files\Okuma\THINC API \THINCGrinder

THINC-API libraries and Visual Studio Brower Help files:

- D:\Program files\Okuma\THINC API \bin
- Okuma.CGDATAPI.dll
 - Okuma.CGCMDDAPI.dll
 - Okuma.CGDATAPI.xml (Visual Studio Brower Help files)
 - Okuma.CGCMDDAPI.xml (Visual Studio Brower Help files)

Logging Service folder:

- D:\Program Files\Okuma\LoggingService2
- ApiLog2
 - Okuma.Api.LogService.dll
 - Okuma.Api.LogService.WinHost.exe
 - Okuma.Api.LogService.WinHost.exe.config
 - System.DataSQLite.dll

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

6.2 Desktop Installation

All 3 libraries for Lathe, Machining Center, and Grinder can be installed when desktop installation is detected. The installation will consider desktop installation when there is no OSP-P folder on C drive.

All libraries and applications will be installed for each selection of machine types.

7. Installation for Custom Application

This section describes the process of installing custom applications developed with THINC API libraries. This process allows custom applications developed with any version of THINC-API to run on machine without affecting other custom applications running with different versions of THINC-API libraries.

In order for a custom application to run on machine, the following steps need to be done as listed below:

7.1 THINC-API Spec. Code

In order for THINC-API to function, a spec. code for THINC-API must be enabled on the machine. To enable THINC-API, it must be requested through distributor or Okuma Software Group. Currently, this process is done by installing the OSP System Software on the machine.

On Machining Center, THINC-API spec. code, **CAPI on No 32**, can be verified visually on the NC HMI screen as shown below:

NO.	DATA BIN	HEX	BIT7	BIT6	BIT5	BIT4	BIT3	BIT2	BIT1	BIT0
21	00001011	0B	TPRB	TSNS	ATRT	DRME	DNCE	PRNT	TLLF	TLCH
22	11101010	EA	CV10	CV2	DNT1		DNT3		DNDT	OHSP
23	00000000	00	YAEC	NSRC	2TOF	DYNZ	DYNY	DYNX	ITPG	TRNC
24	00000000	00	MSB7	MSB6	MSB5	MSB4	MSB3	MSB2	MSB1	MSB0
25	11100000	E0	LSVP	MOPB	LNRP			SHNC	NBS	SHSI
26	10000011	83	TWRC	STRC	PHDG	MSKP	SATM	SAMS	MNMS	SPAE
27	01000001	41	ANCR	EXIO	PHAR		SRAC	NACF		SYTP
28	10101001	A9	CLM	Z100	G68S	CLDC	CHMF	BITL		PB12
29	00001000	08	PHD6	PHD5	PHD4	THSB	Z200	F1FD	IGFD	THCM
30	00100010	22	FSPB	DPDI	NRSP	TNDM	WIOP	NTHC	HELP	PHD7
31	11000000	C0	OACS	EXMC	IGFA	2SLT	MSUS	PE10	PER5	
32	10000101	85	NOPN				BRLT	CAPI		KKMN

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

On Grinder, THINC-API spec. code, **CAPI on No 22 bit 0**, can be verified visually on the NC HMI screen as shown below:

NO.	DATA	BIT7	BIT6	BIT5	BIT4	BIT3	BIT2	BIT1	BIT0
13	00001001				BAPR	ANSA		EMR2	EMRN
14	00000000				VLMC	SDBK	WKWT	FEDRT	ASTF
15	00000011						SDFP	SDFS	SDFN
16	00100010			GPGA	GI			EXUN	INUN
17	00001101					UTSK3	MSG	IOVE	CSHT
18	00000010				LDRS			WAID	
19	00000011				MDRS			IGAP2	IGAP
20	00000000								
21	00011000		EOFS		EOPL	BOPS	OBFX	MAMD	
22	00000001						TALM	OAPI	CAPI
23	00000001							CEMSC	MFU
24	00000000								

Note: There is no NC-HMI screen for verifying spec code on Lathe machine.

7.2 License

All **THINC-API libraries** require a valid license file to run on machine. The setup itself includes a time-out version of license file and is installed in D:\Program Files\Okuma\Licenses folder. Your custom application or demo application can be run in this trial period.
It is possible to have 2 type of license files can be coexisted in the license folder.

7.2.1 Flexnet License File

For Flexnet license file, the file name will be okuma.api.lic.

Note: This license file cannot support alphanumeric machine serial number.

Currently, the trial period is fixed to certain date in the license file.

For example:

This license file will be expired in Oct 1, 2008 for Okuma.CLDATAPI.All version 1.2. This license file can be used on any machine.

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

FEATURE Okuma.CLDATAPI.All okumausa 1.2 01-oct-2008 uncoun ted \
HOSTID=ANY TS_OK SIGN="00EB B55A 56DD A45F 75D6 F491 231F CD00 \\
2BA2 A406 AE0F 932B C574 7230 959C"

FEATURE Okuma.CMDATAPI.All okumausa 1.2 01-oct-2008 uncoun ted \
HOSTID=ANY TS_OK SIGN="00D7 1F45 6055 FEBE 8654 2089 A431 B100 \\
EE6E 0E40 BAED 4AA3 B350 78DA 8955"

FEATURE Okuma.CLCMDAPI.All okumausa 1.0 01-oct-2008 uncoun ted \
HOSTID=ANY TS_OK SIGN="00D6 079F E750 1E50 F866 794A 9058 3900 \\
7BA4 97FD 199B 9809 7F19 DD09 41FD"

FEATURE Okuma.CMCMDAPI.All okumausa 1.0 01-oct-2008 uncoun ted \
HOSTID=ANY TS_OK SIGN="00B3 3BC6 ED99 A792 24E0 A99C B6D5 9000 \\
CCF9 B436 0BDA 7283 CCAA 5BE6 E6FC"

FEATURE Okuma.ControlType.P200 okumausa 1.0 permanent uncoun ted \
HOSTID=SERIAL=105330 TS_OK SIGN="006A 4D47 5A17 E95C 4AC1 1494 852F \\
DB00 A98 F8BE 5366 B02E 10E4 1220 2FCF"

The non-expired license file must be obtained through Okuma Software Group if you are a customer only. Each THINC-API library will check this license for correct version. The library version should be equal or less than the version in the license file to run.

Sample valid license file per machine serial number:

FEATURE Okuma.CLDATAPI.All okumausa 1.1 permanent uncoun ted \
HOSTID=SERIAL=105330 TS_OK SIGN="00C3 4CCD E2DB 439D 0F83 4805 \\
9C14 DF00 291B D46A 71BD A96A 61A0 5A54 D18B"

FEATURE Okuma.CLCMDAPI.All okumausa 1.0 permanent uncoun ted \
HOSTID=SERIAL=105330 TS_OK SIGN="00A3 F5EF 4872 1C12 27C9 8E5B \\
C5B9 4D00 5300 1FF5 D0B4 1371 DC59 4FB9 CEDD"

FEATURE Okuma.CMDATAPI.All okumausa 1.1 permanent uncoun ted \
HOSTID=SERIAL=105330 TS_OK SIGN="00B8 7E90 2B05 9535 94E4 92CB \\
C8BB B100 89C1 3E47 820D E045 931C EC07 68A9"

FEATURE Okuma.CMCMDAPI.All okumausa 1.0 permanent uncoun ted \
HOSTID=SERIAL=105330 TS_OK SIGN="00B2 0B95 F2BC 0E10 D351 D60A \\
60F8 E100 1904 FC87 685A 09D0 A1BC 1C45 8B52"

FEATURE Okuma.CGDATAPI.All okumausa 1.0 permanent uncoun ted \
HOSTID=SERIAL=105330 TS_OK SIGN="00B8 7E90 2B05 9535 94E4 92CB \\
C8BB B100 89C1 3E47 820D E045 931C EC07 68A9"

FEATURE Okuma.CGCMDAPI.All okumausa 1.0 permanent uncoun ted \
HOSTID=SERIAL=105330 TS_OK SIGN="00B2 0B95 F2BC 0E10 D351 D60A \\
60F8 E100 1904 FC87 685A 09D0 A1BC 1C45 8B52"

FEATURE Okuma.ControlType.P200 okumausa 1.0 permanent uncoun ted \

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

HOSTID=SERIAL=105330 TS_OK SIGN="006A 4D47 5A17 E95C 4AC1 1494 852F DB00 A98 F8BE 5366 B02E 10E4 1220 2FCF"

This license file is for machine having serial number 105330 only. It will not work on other machines having different serial number. It will support Okuma.CLDATAPI.dll library having a version that equals to or less than 1.1, and so for. This license file can support function calls for P200 or newer control types.

7.2.2 OAC License File

For OAC license file, the file name will be okuma.api.xml. All THINC-API library starting from public release version 1.26.0.0 can support OAC license file and can validate with machine using alphanumeric machine serial number. All THINC-API library files that can support OAC license file will only validate with OAC license file if license file is existed in the folder.

The license file itself contains similar license information per library as shown below:

```
<?xml version="1.0" encoding="utf-8"?>
<LicenseFeatures xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
xmlns:xsd="http://www.w3.org/2001/XMLSchema" Version="2.0">
  <Features>
    <Feature Name="Okuma.CLDATAPI.All">
      <FeatureVersion>4.1</FeatureVersion>
      <ExpirationDate>12/01/2024</ExpirationDate>
      <ExpirationType>ANY</ExpirationType>
      <HOSTID>ANY</HOSTID>
      <EncryptedData>
        ZEDZER3h4T+hWkdOLNwdFakIFh/v7hxbIsy50ivIvx5xo8vTaCYvE7LSqZfZ3w2nSERkjliftA3t
        h6sJC0W1TRoy4WDH6KKJKYSxZ0ShA8zFMr6k574rq
        F+Zm48dxuXcN8gwPwAQpMDgi/M6QhaJ+oNGd5Xj3BMtUGjEshXumFuBueUtUr8tgLJCICS
        7UH6PrDs8wIOd2m8pUp5qNR1IDV7MtfIgsWz8F7xrH6
        TFZKsTbpnWNV+qEFqp9E5/cVSRDJXZ4OY1od7jtjptdiPHGXtMsg8DHBuJz1WlkMkqsPieH
        WInpKf7qEpLACrrFZc4myyL+kt2NUt+mln7OY4xakWe
        1oU3jmcEuWeYxnuIE9YESZd35tZUz9Gc+oL9LW3oEbywSwnf4xrSe21aVhd1Z86O14b2uwN
        BT/df16qIZpIyaa73HANgwojWPY6YFd+WE+nuWkxsqU
        lGmaVY9qwqyDCpjvw13dTXNqCU7K1/cPSRak1NE5RF5hptcdeKFiHHLfOWWleKt1GxvyO3
        pIoo5niLS6fnNxy8RA0uY15fQZhborm29YHWVXqBXa5
        zD3LG3BVj1XHGI/kEIAtozCJPuzT/OAE/MtRcJmZde0TomN0a6VgxLYfCjnQ1CWN00ab9AC
        Je4IYhCYQgMXZH6XIwMi97ox/VhgtuB4xgJytw=
      </EncryptedData>
    </Feature>

    <Feature Name="Okuma.CMDATAPI.All">
      <FeatureVersion>4.0</FeatureVersion>
      <ExpirationDate>12/01/2024</ExpirationDate>
      <ExpirationType>ANY</ExpirationType>
      <HOSTID>ANY</HOSTID>
      <EncryptedData>
        BRNbi6WQOk7BLf6o+Y91JcaW7t+k9aL/Ek9sSsrfW9cDpahrYUJdf6MVhVyyYOyK0puVvwd
        quM/MVOFKnP/dQvLBkI/KQwMRLFh8mJ3QHqZU1q2GjIYu2vR4T
        Y2pcR2xx5qz1a4u01VqLw2yIGGUbB3xXpQ0at6jS47Xho3p2ppeYjJXN1/+jdWWyBnyHYslD
        QbJtN668m1S7ezYvhX0rUnYPD7ZwuR3zAVKy/x+Ikju9gxllul/OXIRE
        AsdfEow+Iiy22imyHKBK865ljqKngk4z/hJK6VETLD6qHhRzY+k+7UYENTG+cOmXgmWpL
        tQDaMUyPJiumd2ztPs8GOD1buFkQ0SIoBrCm6oFX2AAZCrX+umU
      </EncryptedData>
    </Feature>
  </Features>
</LicenseFeatures>
```

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

bEXbcJS4YGwdAluX7a2q3ysVRvV76vggBSCjCow+SxVMVVXvQylon9VaVjhVrWIGZ+DgG
8+r3wAglGHaWsxWAKNrmb3LyYmuO9cA++u793d5+BNnsOC+Lu2
fyobWe649vyGh9BdMeJUy212mufGF3wQiKAPI3k4SdeVBpx/Uf0D8E8a2P2hIqgadkGaOuovR
YCIFsdNwOU6rrb9kffkPD9lUob4QZwCdtkz4DiS41bGOzoFkZHofX
6yRSPemlunEp4XZY+Xj7BjGjX1TuTEMJaQaWmVQNYm/4xQ+MOu2tz+S3y2ACUkaf+Y8=
</EncryptedData>
</Feature>

<Feature Name="Okuma.CLCMDAPI.All">
<FeatureVersion>4.0</FeatureVersion>
<ExpirationDate>12/01/2024</ExpirationDate>
<ExpirationType>ANY</ExpirationType>
<HOSTID>ANY</HOSTID>
<EncryptedData>
kTiG/yu+HjRRInm//jGehj7p5JoHt2Swd4CayjNU3EqqTdUALR8q0sF/U2Fb2KVGd8a0rUE6VD
YlgxGALi8eMTQgiBvPeRsjKvaHwpupoOB2JS9tVO1UJcnv80qpXxCK
ITpA8c8drqRdsC61TA6gpvZ7IouOtJYK8OmA4EBpcSV1bNrv9qkwPzg6Rh/SpbD/ySjLrmVim7
JeBSxOpcqvBoTxMhq6ASxunEkQUnb6x6NJGCvP4Ta9UYqMnVjX1m
hj9DRb/JSzj7fMk9GieGamU7Y7YqIHYSb1aQP8LiExmDaxiIQFkNDUnJ8VyN/Zk+IxyGZd3+L
VZTAXGuICupmRDplqP9g9eM/JmMPHiw7y7MWaaOibOVMEytj0FYA
dSSw3Hb3fQh7o/NtJcwon0bsBJ2AY1bzriPJqvymI0of/XzaFWju8kQsszYKSoM3OcfIt62BFQQx
mlOhR0FYtr9lRkzmEbGHlfUs/eHC8HfziBWHrcX+4FwLYUv6pe/O+Vw
bcrSMXPqjAk6j3odvCYgywV81CtzC/1bIuwQNRgO43z5h6IdRpgVKHDDQJgeG5qhuPfihun4lx
5gDp1VTbtqAPZGngdaXtm9UQX3vBNsfbeeDNpyPTsS+p9ptAtk82xhiAp
nMPcs4Ipicll8/j1ksRVjLtRwFK6X9id9fPuX2Gw1M=
</EncryptedData>
</Feature>

<Feature Name="Okuma.CMCMDAPI.All">
<FeatureVersion>4.0</FeatureVersion>
<ExpirationDate>12/01/2024</ExpirationDate>
<ExpirationType>ANY</ExpirationType>
<HOSTID>ANY</HOSTID>
<EncryptedData>
CXfalc6jIaOmmAYMOpuH/zlVwF6Ae0WzxbtUNbmRs7O+QyHv3P/EG2bfC9MeDnG09b71044
+CG1dHT6NqAi5+11VvH1AVp52YR7ePbFkoV6w7qEX857XEv9zjzPfrk+
bG6pjmGF9okJtLQcS/bMIJYUsN19ItTKe1ZEWRtnTKVv832DSBm6A3Dkho0HvHTxN3vs6E
ToGKg2LMUM9AZap2fbooVky3mYbQYhNiB7+4aoGfjMIgh6UenSCqQltt
zu90qGJ9DvDAA/yPL1Q+dV/jl6TViYTYdE6dVJpEshIXV8m36T0yWnGxy8fFEmQYckyLuuE
TzeVCWzKScKI1iVG3cY4qFVXifc23Cjj1V3tzRqn7NE4l6GL2G4ljKxp5W
YwjnkmuEE7R+hToh/f0eTl7Nb7KukUOnZjvPDMNabpYCZyimmqCWMw2zQ384mNQyGB5V
sUcXis5fDxnJs1OphHaZYCK5NC4gOKImGwnly63jFWy9S5PYx6F2BEnL
ybaMsIFgxHNj/Z2CZcq+y4oABCVE/iSqB2AGYmCJLRophhrkDkqHp/f9U8+7U00QifEXR6gI
Y5gYcE5t/V2jzxRWAue90BLshrs9EXNrLkHAKc5qgVrt+411flhe2+925sbX
i1VQjWCzpV0HOXwR7yL4mgor2XdRr3kBqN6qiwaDNGeY=
</EncryptedData>
</Feature>

<Feature Name="Okuma.CGDATAPI.All">
<FeatureVersion>1.4</FeatureVersion>
<ExpirationDate>12/01/2024</ExpirationDate>
<ExpirationType>ANY</ExpirationType>
<HOSTID>ANY</HOSTID>
<EncryptedData>

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

Tca+cnV6bZBY8Bfl0Zg0KEUbS6mbXDWt/UPAS1+f46S2pRQzaoHbUU+OFXFiBj5RKHWc7
hqE7Clt1Q49KEhQUwtDhS1pD0rYegQje+PrFem4TnV72eBwgKx1knwRSy9L
ZcyMXVpG2nV6dThhMcliqv1+0WFgqFRxoAeivSVDhF0x/GQq7D72WMuHidr/sVyKPuXOiW
bFg0vonLvEiKYRkgt/xIqcG9yyOIG+ySDfS1WWwm9ksRodrdb4GoxaTK5rLq
wTj/teWa26XBkYZsGpeAobPyusRqnJwPOzAQbjFP7E4DdpCE2DF1gYoNmRN0zA/IZaKU1U
F5VZW08q4ps0pQRNixmI/nvR+1d4uPWb6nVU5IuJqxf5pNgBUTEZWXLNve
n9u47TAXkn42GsSg3r/2VcYKMYdVd0fuKGizWUEKqm7tFYf43gN1qmJ+j8muHmLIKmkJdG
2BXF/F/AwJgWgGGeQJCu3X+OpknnA12fhEPshVISH1DIS0QPFNIIO3JuPD
1Dvv2gn20nhIdYvL6aKM5GYDtevaZeka6d9XZbyqZu/zKmijZyvDToVBgDYf+9BVo+UwTX
keKJ7Gv+PWtl9+7dqjDOK5CvOlnQQMw97nE/loGJ8e2tD9CO0sJp9nBWJAup
RMww9e2BOxRqDIlfNtQPQFTO4qcSiSbZipQXx4=

</EncryptedData>

</Feature>

<Feature Name="Okuma.CGCMDataAPI.All">

<FeatureVersion>1.3</FeatureVersion>

<ExpirationDate>12/01/2024</ExpirationDate>

<ExpirationType>ANY</ExpirationType>

<HOSTID>ANY</HOSTID>

<EncryptedData>

EMrxOTdOvT37lqjnZ8LsfHso3QWYiADthPiNAw+PC6/RTdc37qipoyuqlBRVL0jQQiLnEEemQ
WXj0qUkXOEoMcGfYkC9wMN4A2HrwPx/b/J2ExjAM84PJ/WQFA0P5H8Ief5
8SZ8Uu0Jh9xLbNQRACKjwXTBU3BfDw1pjY5xNjOjY3akojKgflisHcaBjUCsEXijGwSHdbHfE
5RtXrZvhLdOVqq8Zdk8+OiXajvp10d6WqlUe+mUe+2iycuDnN0xpF+Y46YfsS5
sSwlT5YW4lk6inQWi/bs95T1oj52u3qKrnb8aN91Fw6VMM1DmFRHeIIW+MTmjY82fDHFQ5
UffcyIYFk7gXb/5w4sH1Yft8fvmalHeyQSI5rdCPCsXugVwCh/Nm1AlAR0d1AW
BTDJZcPITXoAltbp8lvuJX74wBxBCs7Su5XVhMO5Id4VJeXTdO9LnOWq8hERzuC4ivOb/rY/
SMKayxhHyknKJvSa3q4QMjhogr2hsQnDuZqR9/j1iX9Bmfqf3qAdBelnpEi5RL5
Yh6zIJ95O/moM/Ki788LJNp0rksn2nYTCvbWuplh8kGwtg8mSj5eq5mlU3P860eDJr9L1xcZPfs
0S5W/HAd6jpNkJoZvVcYg5rXphYe0RsYoG+le9FeUC+74IsnYGshnY97/eb0kGz
FTSYf9RjFM=

</EncryptedData>

</Feature>

<Feature Name="Okuma.ControlType.P200">

<FeatureVersion>1.0</FeatureVersion>

<ExpirationDate>12/01/2024</ExpirationDate>

<ExpirationType>ANY</ExpirationType>

<HOSTID>ANY</HOSTID>

<EncryptedData>

IQmHglll/kv8VuyO7fIWAS4IW+mzeEul0zQsyXAocL19zay6E02k7graEfeI14yXl8ZC2wopDdu
GzjiEPRU8Rv1AsZfjmqXIo46SuDN5EQeB39oqqET89XiwmkP2sP/UYddQwp8Q2A4PoT3D
EXjO4TGUO5oBYTHHmDM3qQWmIr3DkssBeS6SHRSj3LXS3219uOJ5RLaqW46I6xC/z5E6A
XBARYZ7YJ217ZQUJRb9gH6DzOiyhc1lEM7ptMWBRURQo9G72KcpG0P7tQaUwCbqdg
i6K9JO53mBaNJzonhkNvaMwRGR8zTB/ON7ppDu4JxgafAibGULiilNdGvuKJ1Nz7HOfNvBv
LYz8FhPj+Py+cfM2GphtiFfbmM235JHY04MBI5laPLgHWj9Nly20brihzLMcmYOlI9eJmh0
EexWEfX0ddgyLED9/7GbeDB+unPebYt14c1sF12AHQjAsR2IOHIN6re+JYnhh1eNmgPQqerP
YDrcZXBczKL6RsDuZ+puKHwS9Sjp9GfvkzAPRhK/jZcT9olNWO5xf137zbIOH5426Jmq2D
Epmnq/UVZ4T665v/iRuWR2KGoLA78lxCCA7CoFhFABhhmym//+05Uixh3ccPx/w7s84A+r9+qf
v/jgSR4MHQdh+LTdoWqxPWdZG6Mg/17h5E6wJdky6H+PjXc=

</EncryptedData>

</Feature>

<Feature Name="Okuma.CMDATAPI.NCCurrentAlarm">

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

```

<FeatureVersion>1.0</FeatureVersion>
<ExpirationDate>12/01/2024</ExpirationDate>
<ExpirationType>ANY</ExpirationType>
<HOSTID>ANY</HOSTID>
<EncryptedData>
  Q00mACXqFej8uABoY3spP1kp2EmM7IK6iZMzF5+d39h7eklWLOGrD5X42ydrPg1Afy4u+dbf
  1ufdtNjAql4nDMI99lSEGOL6ZUz4Q/24iVn9lmc6BxJmdS+y/W8GswrSaXZz2GkRy+rVL
  dKa6Gq+iGmWTO5FcRfZNU440fUNXLoGccwz9LZcNF/b7LQV6Ovh7RF+qM38QrvXRr5+t4
  KLUF4BwjGYn9FBAjxa9PI6/xqztq1DY1SI5ojPIHNkOBcQUFQ3vsqgAhKcwciJvaz65e3c
  VzpoesNAVanpvgORMDX1n0+QZAg9t4ePS02wMtxGwZNmgsFuC15AnraLPQs+jHjeLKKt1y
  wzxjfmIah2ugpD1hSNCfD4P2Dy/m332GESaDht5k69zbZqR+IqNAfxdASo/HYqJF9oUYT
  c/ba0hVrmGG8xXxD7ORnk/LDG6b/0PJG0kWhhA9e+2oaMWnecqMOjsm7ipBDtQ/BQZvcQ0
  ANQ/L/8IZioRMKyv7zLW2l/oAyW18QzHjWFZa6hluL0ZKIN3SOIHhQ8183WYpwdG3Y
  /abaSt4OrDJ/Teomsl8tXvy6D9u02od00pCxwmPf6wR0f2l2vDN+kQsQ0emZg7goQF8PqXnse0j
  Ey5Cp4QBtIDUBW5TezU+I3ptY41cD16WT8eFYRMYX9aF0g0v+sTA=
</EncryptedData>
</Feature>

```

```

<Feature Name="Okuma.MC.8DigitsToolID">
  <FeatureVersion>1.0</FeatureVersion>
  <ExpirationDate>12/01/2024</ExpirationDate>
  <ExpirationType>ANY</ExpirationType>
  <HOSTID>ANY</HOSTID>
  <EncryptedData>
    FkrCyumVYUgTUXIQzAMZyU8l4p8PTrxvyTPwlijftygeLWSxgS3PWppPU74GcZALsMOtXhe
    rMYDicKOLkN663IRJGop7Xig19i+fvrhQvwfs6iuw3+eAwRdZPUUoMGUE8aU
    1dftjIvM1qU663h3E68o5+s78b9B8cW6zaUAw5A64TgUI33T9CBU1ebOGoSfYGEoNp+vQJh
    XIOMTH3dPoa51wJl9nlie3iURBZnyyB3qNdPKFA0zvFUVwqGtsgxHnlz1rCRgff
    AjySsmI48hW5RPnEzS9cOwbqF/OvAiA1bYCPSPXpwSafxNg6v37+u3mzo67ZwszLno8VNA3x
    Qy4+FvuIV0xOtOTzWwCj9s6MYAHGxqSGS9vS/aPzS20CQV9NXEjaMzwOIqtb
    mn36Uu2/VYcjFwP9+pUs+X45AwhiXDR4DKd39jF+zoo0JTTUud3FsIezb6vb9Q/pRmUyk9iI2
    NqLsa2lMP2Qz6zSlan9WQBvnYbTltmJ2J8kJggIx3eWYcwwokDFG7qz6PXFIt8iY
    ojdJatKGfeaKaBJPJnUzP9zS48yGGTRAGJbZnCww+iJXfOR1iZ35DjbvtV+cVXVa9yI/baymf8U
    x0UURaFTId26pKkCV8RRH3ondexOuYTYI/EdVnWZ+2FLtF8Gx3vne8DFIUXjN
    X2UdFIRqmYNQ=
  </EncryptedData>
</Feature>

```

```

<Feature Name="Okuma.MC.UserTaskIOVariable">
  <FeatureVersion>1.0</FeatureVersion>
  <ExpirationDate>12/01/2024</ExpirationDate>
  <ExpirationType>ANY</ExpirationType>
  <HOSTID>ANY</HOSTID>
  <EncryptedData>
    EOHbAypAY7lG4xsFf+bEciIKphD5ZepNdPtEx4YC9hLuAQ4n4bkf6Xoae+82YuQUxjwRrUX
    Vt8sjOxyIwu4UvvVRLBTKKyeEaacyHn0cSCKdxfZQVf295a3YYKJHvxR1Ah3eI9
    fkgUA8XtbspFGZ1VUy0JqQx+1lYb83jKo95wsZ3jRjBmNJ4iTb11XtKtjWT4atJqv5yH+MF0bR
    SUwDUYDYUENNmWP1lQTYzzZbQtj7R9LupEpAoBiUemfFwenfzmaSjAE+Y
    MjADIHckkfOzBQ+J92J0Po+rs+imyKoJlsDddTyQ0BzhdD3BaB0IVvheAbnSwmo+ngeWcg8d
    Dj2iUqEBiUxHv2Aq0A1ah/lyBMjDF2XQTOGEQBZuPEQaEhwhAO8raGrs5J
    sTibf1WME4pCKxmAtMYCgknZnpK4ClbXKfmdNixjBk/gph9oSCdydbksrn/Q10fjzYqQ8IsW13
    9K/04Uafu8OWGEdTzFLMzuqRtjYzmJt+I3izQTOA8uqScUxxEQCsS1SJG5jVs5tY
    GI14vt6V2y4T6FlqJgGWy8hpf3KPF1/upu+5R3V+anW8Ksk6Ynr6UQkRHj3qQd+VXHxVJVT
    /JxAfSWmalwAYSSXCbVgR4Y2ocRWPiXmX+dP6oGgvbrMsWSPI7qttQjewWvM
  </EncryptedData>
</Feature>

```

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

```

Dg1CIP69qIEXk=
</EncryptedData>
</Feature>

<Feature Name="Okuma.Lathe.UserTaskIOVariable">
  <FeatureVersion>1.0</FeatureVersion>
  <ExpirationDate>12/01/2024</ExpirationDate>
  <ExpirationType>ANY</ExpirationType>
  <HOSTID>ANY</HOSTID>
<EncryptedData>
  oZPtP1zQbWrP0M6mXvqpbBLb8jBNeddFVQyvKXHBbomYU/t1JAumjSo82gx3W+VAFtuv8a
  EHF3OAOd6HyTURk8t0pVuLz0oG8AAzVb7FiIBJPrqaHDbStBWx5ZNpScnlGYz17
  dVmkt0iA27+yRmDeYXKMnCuPa8mq7TG9HG+rCJtYAh8tI5A2QG1b27JI9wxg4t41UQ+CV+
  fwZOb2dJupjJbRC4ncQ/G5jpp2/HHVLkZg4iczotFr9Ygv2z/7ob9DqtPnsial3A97A3TQ
  461IHtU1P0BaA5T4FFsjIE9EeSq7vhaouFIKr2IEUuUw7uBWxiXjsNERUZcYQJfFEcwG4jdrTo
  JHcSqqTVVJgmWAqqrndJ3DFPOZfNTBGfTJTecGIOTUoGZnJs1EJp/LxAceTDMplh
  UjKgeMXPF/+4Ou7PteuaXwyk9oEl7KkdjIFimaRQVrhFFuwn9ZkjJzkHprMi7CX5b2vYzFACS
  aFU9Oxq3d5QxmNHsdEJO+akp75AnLtQGkhj+ade9R9nqLRXPHUCAmLz7/KGfLZ/6
  +5syPkVUgbPFpuAGjJphjakdWJ6ry01+nAyw2d/yxe3nzkrSCmQuGDBJvuLJCmKyWmuuzODv
  Y2/F/GpseLRuS05JXWKDgpbU5zUjotjWXisTJg34Jy9iMkYq6xkka53zgKaIv7E=
</EncryptedData>
</Feature>

<Feature Name="Okuma.Lathe.UserAlarm">
  <FeatureVersion>1.0</FeatureVersion>
  <ExpirationDate>12/01/2024</ExpirationDate>
  <ExpirationType>ANY</ExpirationType>
  <HOSTID>ANY</HOSTID>
<EncryptedData>
  GMDvIRMEe4xzRuClDIXPL4XJnb3Hr02WnivoHNqtnqM8U1qWn9gri1Q1NB8/GME7P6sQK
  Ve6WPJw95GwEuglIfWeTWQHx2EN/qwz8/EGNsSAQmddkGzn+IE62j+slcT693
  Ji6Np0eoclWGky/TJgpcbyybb/VghkZT/O2pbkxWT4qfKR1O1hOuS5X4RW15G0hExj7t78+lcD
  H55rOnvx7vTyeI/kldwAnXxXnMB9SODrc1A3QlNHcr7vICHvfarX1yY0rwTdsH
  pMsyBvJhEeBzChUJWeASXpn6AFiei36eP4hdtgRl8GtXGBJ1bxOjH8x8AjQihHRch3mWF3j2
  HwEvn39VdwIwXCbowntZKVGCSswrDtkJ5omjd3RkcTl1AELPqFMKlKHNTmb
  6LveWUG/J1t6Tz73EpdQLmTcFgfEPBB6p5sjFevM+SjetuTFU8tJ0c0gHncuTRl68AqMl9EJ+3h
  9Ueh8JnKE8WpA+gwa9KRVEe0zhjdArPNoU5NBX993NrXLFU4EH+IxMRHE
  WrPBxwy/gkLCGfDVkC2tSBvtJRPT7gAdxYt1Sf16/juQulrpRCFFoNH8JgBf2BcasW20hoAJq4
  rYy8y5MWhWBD2fbo/zW7lMRnqEL8E88F3f2KWETJzJnj9LK3UgMHwC8Arx
  9N9w/un362M86oSGErjQ=
</EncryptedData>
</Feature>

<Feature Name="Okuma.MC.UserAlarm">
  <FeatureVersion>1.0</FeatureVersion>
  <ExpirationDate>12/01/2024</ExpirationDate>
  <ExpirationType>ANY</ExpirationType>
  <HOSTID>ANY</HOSTID>
<EncryptedData>
  diLq133hHLYVXJq1aZ9Qk4qsR+VeWnmfbraROTBY+k0bIUcQ8vcWwrFt3/rJ5yRkopruaS27cN
  CdKdUnrMBLl0Zr/3l+CDYBKS4DkrLUKOPmqVM8qH9v0ERUEIzexuMyRn8
  bUwQhnA0J0pYJpFoKeH8aqZ9nkHtzVkfYujzDW0TsmvUAvapFqEGOnCRE6YdyyX9AeKUS
  UkmHbuH40SMYkkUUTKEcSmnGqWSspHdVuwTC1f2DdNtiQqUtGyOa3AJ1s9

```

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

```

eaiAlcgNDY4d/MkB02sfP8VdiSiQcev9k2BMFWHkzHxpxxbn5X1IHPCTr3493oSApbt5AZvO
uL8c09fhhbn3KSNbC1FSCvzud25emK510x3spzTik6sOEKBzh8NhbN8ZWOQC2P
N5VR96LGnvZlMrvKymuOKHuEnv+2Hh1YIAkt9xabyGgAWUoXrWMIKK65WU7/Iv9iJXI4
6avci3ouqkf6qG4CFgJZ0r+8OEfTPKRuFwansywUkR0xyGJMCtBL64pULVezPa
8Nqi4fGbSRWEOQ5WqocH98s+bqmtDwgPuEjtsUGbSY7lUbzZOeI6h746pVz7JltQhaUgarCa6
pXOqJh9Ce6rVbw/yx5ZF0KgzK2/vjrqaMASCKK4sgVodSEIEF5Vj34K3YJ7C5iw
iO0SbsUCz5EUidyCm+HKA6sM=
</EncryptedData>
</Feature>
</Features>

<Signature xmlns="http://www.w3.org/2000/09/xmldsig#">
  <SignedInfo>
    <CanonicalizationMethod Algorithm="http://www.w3.org/TR/2001/REC-xml-c14n-20010315" />
    <SignatureMethod Algorithm="http://www.w3.org/2000/09/xmldsig#rsa-sha1" />
    <Reference URI="">
      <Transforms>
        <Transform Algorithm="http://www.w3.org/2000/09/xmldsig#enveloped-signature" />
      </Transforms>
      <DigestMethod Algorithm="http://www.w3.org/2000/09/xmldsig#sha1" />
      <DigestValue>7FnHW7FtmZFCkugKpH8G72lVxjQ=</DigestValue>
    </Reference>
  </SignedInfo>
  <SignatureValue>
    n1FM8Vkyfk0WLzVMGgWPGQNC2aORhMPqFNArO2UXYqEzqEmagJDFvu7ybXbrJ0NNvx
    ntyx8VKjXAfQT9P8Hu1zX6Gce9vJMVBNfalAxH3bCXOB81lvFhOsARvxTvpXru
    2VT3uRvYBEjBrrDmqW9/3QAqFoDn/HUNqN4R5PkGJVqkn8fEZmaMM1EiEqBYRi6Cnhca
    MKGESaFnMSGZVPOUo3gYbcSo3Wdu7eM2KiwwFhnBQ3fn5GszYUYf+y8gWE
    HRv9ydpJy4txAd2UJJTs2o2UuirxSStb0b5Go/sDMKkn6eRHFBTXOfO9muyutLu1SroAjfc3tsdx
    0It8xJcB/D8oKvUhl6qsa/OxTSPieEZafmS7CA2Lg5+37jayFQ/2OVzmWb8Gkdzgs
    8dr4KW4JOIj9b9kudpkCHWNsyozfIRALbfsRXw87NdVNwW2dOnWEZKUNRUPZqluoZ/db
    UuuJst5cu2PVJiJURYWuXp89RVB5IUjke/UoJn6I7Sg6wvzt9m8EbQwJ1aAlkeIX8
    msJLITt5WiRteYtwg2dVsqGVYGz0EKZJN/hRWsHoCNFW6+CkklTdQmSsRS9epvR9ZRWh
    GKxmP6GlXWIEwULPem1oJzfJ8OMjz6kY6b0SnDdAf3LJ2/Ph6kmFNXXMvDmv
    QD74ADaBUzohHCFtOjatzwop6Y=
  </SignatureValue>
</Signature>
</LicenseFeatures>

```

7.3 Installation

As normal case for all Windows installation program, THINC-API Setup will run through the installation if:

- THINC-API is not installed on the target machine.
- If existing version of THINC-API on machine is less than the installing version

For custom application developed with THINC-API:

- All and **ONLY THINC-API libraries** referenced by your application such as Okuma.CLDATAPI.dll, Okuma.COMDATAPI.dll, and Okuma.CGATAPI.dll must be included in your setup and installed in the same folder of your custom application.
- The libraries version referenced in your application must match (exact match since this library is signed with strong name) the libraries installed in your application folder.
- The THINC-API license file, Okuma.api.lic/Okuma.api.xml, installed on machine must support the THINC-API libraries version that your application are compiled with.

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

For example:

The machine has installed THINC-API and the version of Okuma.CLDATAPI is 1.1 as shown below

```
FEATURE Okuma.CLDATAPI.All okumausa 1.1 permanent uncounted \
HOSTID=SERIAL=105330 TS_OK SIGN="00C3 4CCD E2DB 439D 0F83 4805 \
9C14 DF00 291B D46A 71BD A96A 61A0 5A54 D18B"
```

Your custom application is compiled with Okuma.CLDATAPI version 1.2. In this case, the customer needs to obtain the latest THINC-API release and install on the machine.

For all cases, the latest release of THINC-API will cover all custom applications running on the machine and compiled with different version of THINC-API. The latest release of THINC-API always has the latest version of THINC-API libraries and the license file supports latest THINC-API libraries versions, also.

In all cases, the following files must not be included with the installation of custom applications developed with THINC-API libraries:

- **LCMDAPI.exe**
- **MCDMAPI.exe**
- **GCMDAPI.exe**

7.4 Public Release

All custom applications developed with THINC-API must use the public release 1.0.0.0 or above. Any version before public release version will have compatibility issues with public release version and will not run correctly.

7.5 Best Practice

An application should verify all dependency libraries during run-time and encourages using the latest version of THINC-API release if possible. A re-compile of your application is a must to leverage new version of THINC-API features or bugs/defects fixes.

An application must install .NET framework version that it is compiled with.

The installation process comprises 2 steps:

1. Install THINC-API (.NET Framework 1.1/4.0 will also be installed if needed)
2. Install custom application (requires installing .NET Framework that application compiled with. It could be .NET Framework version 2.0, 3.0, and so on)
3. All exceptions generated by API and all set/add/cal functions will be logged. Therefore, the application must be designed to minimize unnecessary log by utilizing Object-Oriented Programming practices or preventing perform set/add/cal functions in a loop.

Example of bad practice:

```
Dim m_objTools As CTools
Dim intValue As Integer
```

```
m_objTools = New CTools
```

```
...
```

```
Private Sub UpdateThread()
```

THINC-API	Version: S5015-007-11
Installation Manual	Date: 06/03/2024

```

While (blnRunning)
    m_objTools.SetSubSystem(SubSystemEnum: NC_AL)
    intValue = m_objTools.GetCurrentToolNumber ()
    .
    .
    m_objTools.SetSubSystem(SubSystemEnum: NC_BL)
    intValue = m_objTools.GetCurrentToolNumber ()
    .
    .
End While
End Sub

```

Example of good practice:

```

Dim m_objATurretTools As CTools
Dim m_objBTurretTools As CTools
Dim intValue As Integer

m_objATurretTools = New CTools
m_objATurretTools .SetSubSystem(SubSystemEnum: NC_AL)

m_objBTurretTools = New CTools
m_objBTurretTools .SetSubSystem(SubSystemEnum: NC_BL)

...

Private Sub UpdateThread()

While (blnRunning)
    intValue = m_objATurretTools . GetCurrentToolNumber ()
    .
    .
    intValue = m_objBTurretTools . GetCurrentToolNumber ()
    .
    .
End While

End Sub

```

All custom applications also need to install into D:\Program Files folder only.